

2D Transport Tutorial Part 5: Dirac Pulse Injection and Breakthrough Curve Analysis

1. Objective

In this tutorial, we simulate a Dirac pulse—a brief injection of solute mass over a short duration—and analyze its transport behavior using both Finite Difference (FD) and Method of Characteristics (MOC) solvers. The results will be compared against an analytical solution generated through a specialized Streamlit application.

2. Saving a New Model Version

Begin by saving your current refined model in a new folder to preserve the previous configuration.

- Choose a new working directory (e.g., `Dirac_FD/`).
- Save the model under an appropriate name (e.g., `Dirac.nam`).

3. Configuring Flow Model Time Discretization

- Go to `Model > MODFLOW Time`
- In the bottom-left corner of the dialog, set `Number of Stress Periods` to 3.
- Set the following parameters:
 - **Period 1 (Steady-State):**
 - * Starting Time: `-1`
 - * Ending Time: `0`
 - * Maximum first time step length: `1`
 - * Multiplier: `1`
 - **Period 2 (Injection):**
 - * Starting Time: `0`
 - * Ending Time: `10`
 - * Maximum first time step length: `10`

- * Multiplier: 1
- **Period 3 (Transport):**
 - * Starting Time: 10
 - * Ending Time: 4320000
 - * Maximum first time step length: 7200
 - * Multiplier: 1.2
- Click "OK".

4. Configuring Transport Model Time Discretization

- Go to Model > MODFLOW Time
- Choose MT3DMS or MT3D-USGS
- In the bottom-left corner of the dialog, set Number of MT3DMS Periods to 3.
- Set the following parameters:
 - **Period 1 (Steady-State):**
 - * Starting Time: -1
 - * Ending Time: 0
 - * Initial Time Step: 86400
 - * Max Transport Steps per Flow Step: 1000
 - * Time Step Multiplier: 1
 - * Maximum Step Size: 0
 - **Period 2 (Injection):**
 - * Starting Time: 0
 - * Ending Time: 10
 - * Initial Time Step: 10
 - * Max Transport Steps per Flow Step: 1000
 - * Time Step Multiplier: 1
 - * Maximum Step Size: 0
 - **Period 3 (Transport):**
 - * Starting Time: 10
 - * Ending Time: 4320000
 - * Initial Time Step: 7200
 - * Max Transport Steps per Flow Step: 1000
 - * Time Step Multiplier: 1
 - * Maximum Step Size: 0
- Click "OK".

5. Updating Transport Parameters

Since the transport distance is now much shorter (30–100 m), set:

- Longitudinal dispersivity $\alpha_L = 5$ m (Thumb rule: $\alpha_L \approx 10\%$ of travel distance)

6. Adapting Boundary Conditions

- Select the constant head objects on the inlet and outlet boundaries.
- Edit the CHD time periods to start at -1 s and end at 432000 s.

7. Defining Injection Source

Activating relevant package

- Go to Model > MODFLOW Packages and Programs > Boundary Condition (Expand) > Specified Flux.
- Check the box next to Well.
- Go to Model > MODFLOW Packages and Programs > Post Processors (Expand).
- Uncheck the box next to MODPATH to deactivate it.

Defining the Injection Point

- Select Create point object.
- Click anywhere on the grid to place the object.
- Name the object `solute_injection`.
- Go to the Vertices tab.
- Enter: X = 400, Y = -550
- Go to MODFLOW Features Tab check the box next to Well, and do the following:
 - Set Number of times: 3
 - Enter the following injection schedule:

Starting Time	Ending Time	Pumping Rate (m ³ /s)
-1	0	0
0	10	0.001
10	4320000	0

- In the same tab, check the box next to SSM.

- Set Number of times: 3
- Enter the concentration loading as follows:

Starting Time	Ending Time	Concentration (mg/L)
–1	0	0
0	10	100000
10	4320000	0

- Click "OK" to close the dialog.

8. Placing Observation Points

Insert a new point object at a distance of 30 m downstream:

- Location: ($x = 430, y = -550$)
- Name the object `Obs30`
- Under: Data Sets> Required>MT3DMS or MT3d-USGS ,
- enable `MT3DMS_Observation_Location > True`

9. Selecting the solver

Set advection scheme to Standard Finite Difference
navigate to:

Model > MODFLOW Packages and Programs > Groundwater transport (Expand) > MT3DMS
or MT3D-USGS then Advection 1 > Advection Solution Scheme > Standard Finite Difference

10. Running MODFLOW

- Click the green triangle below `Grid`
- Navigate to `Dirac/Dirac_FD/`
- Save as `Dirac.nam`
- Run the simulation

11. Running MT3DMS

- Click the dropdown next to the green triangle
- Click `Export MT3D Input Files`
- Name the file `Dirac.mtnam`

- Check `ModelMonitor` and the listing file
- Close the command window

12. Visualize and Export Results

- Load the final `.UCN` file.
- Observe the concentration pulse movement through the grid.
- Open the `.MT0` file and copy the data into the `Dirac` worksheet of the Excel template.
- Review the breakthrough curve under the FD configuration.

13. Run with Method of Characteristics (MOC)

Repeat the same process using the MOC solver:

- Change the advection method to `MOC`.
- Save the model in `Dirac_MOC/` and run the flow simulation.
- Run `MT3DMS` and monitor mass balance in the listing file.
- Load the updated `.UCN` results and paste the `.MT0` data into the Excel sheet.
- Observe the breakthrough curve. MOC results typically show sharper transitions and minor oscillations.

14. Analytical Comparison with Streamlit App

- Open the **2D Dirac Streamlit App**.
- Enter the following parameters in the Streamlit app:
 - Released Mass: 1000 g
 - Specific Discharge: 0.432 m/d
 - Toggle the switch for `Source equivalent to model cell` to account for 10 m aquifer thickness.
 - Longitudinal Dispersivity: 5 m
 - Set breakthrough curve extraction at 30 m.
 - Set maximum time = 100 days, and concentration range = 1 g/m³.
- Download the CSV and paste into the same Excel sheet under `Dirac`.

Interpretation

Compare the analytical breakthrough curve with both FD and MOC results:

- MOC shows excellent agreement with the analytical solution.
- FD displays significant numerical dispersion, resulting in a smeared response.

15. Summary

In this tutorial, we simulated a Dirac pulse injection scenario and examined solute transport using both FD and MOC methods. The breakthrough curve analysis confirmed that:

- The MOC solver accurately captures the sharp pulse shape.
- FD suffers from numerical dispersion under such conditions.

The analytical comparison highlights the importance of solver selection and temporal configuration when modeling short-duration events.